



SD & Quantum Offline Software

If you are preparing sessions to run on a console, you should use the same version of "Offline" software that the console is running.

For Consoles that have software extensions (e.g. SD12-96/Pulse/Theatre), the same offline software is used for all versions of that console and the required extension should be activated by going to **System>Enable Extensions**. No password is required to activate software extension in offline software.

Although there is normally upward version compatibility, there is definitely no downward compatibility and therefore using the correct version is advisable.

Many users worldwide regularly use the offline system running on various Mac's, using a Windows emulation program, such as Parallels, Boot Camp etc. which are widely available. Sessions created like this are fine for use on your SD console.

Installation Instructions

The Installer program will install the current offline version of your SD or Quantum series console. If you already have a version of that Offline software on your PC, this will be placed in a folder called "Backups" in "C:" partition of your drive labelled with the date and time of the new install.

If it does not already exist, the installer will create a folder called "Projects" in the "C:" partition of your hard drive where your sessions will be saved or loaded from.

If required, an update for Microsoft C++ will also be installed.

1. Run the program the installer program. The Welcome screen will appear.
2. Click on "Install". The program will now install the latest version of offline on your PC. A short cut to the offline software will be placed on your desktop.
3. Once the installation process has completed, click finish.

If you require assistance or experience any problems, please contact
DiGiCo Support